

## Removing Leaf Capture Software

There are two scenarios where you might want to remove Leaf® Capture software from your computer:

1. You wish to install a new version to replace an existing version. In this case, drag the existing Leaf Capture application folder to the trash can.
2. You wish to remove the software without performing a subsequent installation, or in the event of connection problems with the digital back. In this case it is recommended to use the **Uninstall** option in the Installer, as detailed below. This removes all system files and drivers that were installed during installation.

**NOTE:** This method does not remove user-created files that were not installed during installation such as process logs or custom Leaf tables. During the uninstall process, the installer locates such files, and at the end of the process displays a message alerting you to them.

### To remove the Leaf Capture software:

1. Launch the Leaf Capture installer.
2. Follow the installation wizard.
3. In the **Select Destination** screen, select the destination folder and click **Continue**.
4. In the **Installation Type** screen, select **Uninstall** from the drop-down list.



5. Click **Uninstall**.
  6. To re-install the application click **Continue**; otherwise click **Quit**.
- The software is removed.